



# TECHNICAL UPDATE OCTOBER 2008

Software Release  
Autotime Software  
Version 6.0.9

## Contents

General information:	Page 2
Single user Express/Premium install	Page 3
Single user t5 upgrade to Premium install	Page 4
Client/Server Premium install (HASP on Server)	Page 5
Client/Server Premium install (HASP on Client)	Page 7
Client/Server upgrade from t5 (HASP on Server)	Page 9
Client/Server upgrade from t5 (HASP on Client)	Page 11
Upgrading from an earlier version (5.0.x)	Page 12

PAGE 1 OF 12

AUTO:TIME  
SOLUTIONS

Western House  
9 Allcock Street  
Birmingham  
B9 4DY

Phone: 0121-773-7222  
Fax: 0121-766-7097  
E-mail:  
[dealer@autotime.co.uk](mailto:dealer@autotime.co.uk)



# TECHNICAL UPDATE OCTOBER 2008

## **Auto:Time Software version 6.0.9.**

Please refer to release notes for full details.

### **New features**

1. Updated font & screen improvements.
2. Three new reports added – Job Costing
3. Flexitime reports now available in Express version.
4. New overtime rules in weekly schedules.
5. Daily schedule list available in weekly schedule setup.
6. Default databases to help supply only customers quickly get up and running.
7. Express software version now available in 50 & 100 employee capacities.

### **Installation**

Before inserting the software protection key, the HASP device drivers must be installed. Failure to do so may render the USB dongle unusable. Windows XP and Windows Vista will not pick up the correct drivers automatically.

There are now three options for installation: Full Install, Application only (Client) and Databases only (Server). It is important to choose the correct type of install.

**Full Install:** Installs all .exe and .dll files in addition to all databases, reports, photos and help files.  
(Used for a stand-alone installation)

**Application Only:** Installs only necessary .exe and .dll files.  
(Used for client installation)

**Databases Only:** Installs database files, reports, photos, and help files.  
(Used for server installation)

The HASP USB key is encoded with the software type, serial number and distributor information. There is no longer any requirement for telephone software unlocking. When the key is inserted at the correct point during the installation, the distributor details are taken from the key and written to the database. The Help> About window will have the dealer website and support email address populated automatically.

In a Client/Server installation, we recommend that the HASP USB key is located on the Server where the databases are installed, to ensure all client users can access the application at any time.

### **Important Notes**

The new HASP dongle is only compatible with software versions 6.0.9 or above. If you require a replacement HASP for earlier versions, this must be specified when ordering. Upgrading to version 6.0.9 or above will automatically upgrade the existing HASP dongle to the new format. Once a dongle is upgraded, it will no longer work with software versions earlier than 6.0.9.

If performing an upgrade, always remember to take a backup of the current system databases prior to commencing. This should always be completed as a precautionary measure.

### Software Release

Autotime Software  
Version 6.0.9

AUTO:TIME  
SOLUTIONS

Western House  
9 Allcock Street  
Birmingham  
B9 4DY

Phone: 0121-773-7222  
Fax: 0121-766-7097  
E-mail:  
dealer@autotime.co.uk



## Software Release

Autotime Software  
Version 6.0.9

# Single User Express / Premium Install

The following instructions should be followed to install a single user **Express** or single user **Premium** installation:

1. Insert the installation CD, select the **Install Products** menu and select **Auto:Time Software**.
2. Follow the on-screen instructions and leave all options at their defaults unless stated otherwise. Ensure the **Full Installation** option is selected at the appropriate time.
3. Select the **Hasp Device Drivers** option & install the HASP device drivers, following the on-screen instructions provided.
4. Once the installation is complete, exit the menu system completely and remove the installation CD.
5. Insert the USB dongle into the computer and wait for 30 seconds for the device to be initialised.
6. Run the **Auto:Time** software as normal.

**Notes:**

Default installation path;

\Auto Time\Auto Time Software\

The dealer website address and email address will be populated automatically within the Help> About screen.

PAGE 3 OF 12

AUTO:TIME  
SOLUTIONSWestern House  
9 Allcock Street  
Birmingham  
B9 4DYPhone: 0121-773-7222  
Fax: 0121-766-7097  
E-mail:  
dealer@autotime.co.uk



# Single User t5 upgrade to Premium Install

The following instructions should be followed to upgrade a *timeware 5* single user installation to a single user **Premium** installation:

1. Insert the installation CD, select the **Install Products** menu and select **Auto:Time Software**.
2. Follow the on-screen instructions and leave all options at their defaults unless stated otherwise. Ensure the **Full Installation** option is selected at the appropriate time.
3. Select the **Hasp Device Drivers** option & install the HASP device drivers, following the on-screen instructions provided.
4. Once the installation is complete, exit the menu system completely and remove the installation CD.
5. Insert the USB dongle into the computer and wait for 30 seconds for the device to be initialised.
6. Run the **Auto:Time** software for the first time.
7. When prompted, locate the original *timeware 5* system file.
8. When prompted, select **Yes** to upgrade software.
9. An upgrade box appears in the **Auto:Time** splash screen, detailing the upgrade process.
10. Once the upgrade is complete, the software loads normally.

**Notes:**

Default installation paths;

Old t5 files:	\Program Files\NMD\Timeware 5\
New app files:	\Auto Time\Auto Time Software\
New db files:	\Program Files\NMD\Auto Time\

The dealer website address and email address will be populated automatically within the Help> About screen.



## Client / Server Premium Install - HASP on Server (Part 1)

The following instructions should be followed to install a Client/Server **Premium** installation (HASP on Server):

### Part 1: Server Installation Procedure.

1. Insert the installation CD into the Server, select the **Install Products** menu and select **Auto:Time Software**.
2. Follow the on-screen instructions and leave all options at their defaults unless stated otherwise. Ensure the **Databases Only** option is selected at the appropriate time.
3. Select the **Hasp Device Drivers** option & install the HASP device drivers, following the on-screen instructions provided.
4. Insert the USB dongle into the Server and wait for 30 seconds for the device to be initialised.
5. From the **Install Products** menu, select **HASP License Manager**. Follow the on-screen instructions, setting the application to **Run as a Service** and selecting **Yes** to **Start Service Now**, when prompted.
6. From the **Install Products** menu, select **HASP Network Monitor**. Follow the on-screen instructions provided.
7. Once the above is complete, exit the menu system completely and remove the installation CD.
8. Share the **Auto Time** folder that has been created on the server, ensuring full access rights are applied.

This completes Part 1 of the procedure.

AUTO:TIME  
SOLUTIONS

Western House  
9 Allcock Street  
Birmingham  
B9 4DY

Phone: 0121-773-7222  
Fax: 0121-766-7097  
E-mail:  
dealer@autotime.co.uk





## Client / Server Premium Install - HASP on Client (Part 1)

The following instructions should be followed to install a Client/Server **Premium** installation (HASP on Client):

### Part 1: Server Installation Procedure.

1. Insert the installation CD into the Server, select the **Install Products** menu and select **Auto:Time Software**.
2. Follow the on-screen instructions and leave all options at their defaults unless stated otherwise. Ensure the **Databases Only** option is selected at the appropriate time.
3. Select the **Hasp Device Drivers** option & install the HASP device drivers, following the on-screen instructions provided.
4. Once the above is complete, exit the menu system completely and remove the installation CD.
5. Share the **Auto Time** folder that has been created on the server, ensuring full access rights are applied.

This completes Part 1 of the procedure.

AUTO:TIME  
SOLUTIONS

Western House  
9 Allcock Street  
Birmingham  
B9 4DY

Phone: 0121-773-7222  
Fax: 0121-766-7097  
E-mail:  
dealer@autotime.co.uk



## Client / Server Premium Install - HASP on Client (Part 2)

### Part 2: Client Installation Procedure.

6. Insert the installation CD into the Client PC, select the **Install Products** menu and select **Auto:Time Software**.
7. Follow the on-screen instructions and leave all options at their defaults unless stated otherwise. Ensure the **Application Only** option is selected at the appropriate time.
8. Select the **Hasp Device Drivers** option & install the HASP device drivers, following the on-screen instructions provided.
9. Insert the USB dongle into the Server and wait for 30 seconds for the device to be initialised.
10. From the **Install Products** menu, select **HASP License Manager**. Follow the on-screen instructions, setting the application to **Run as a Service** and selecting **Yes to Start Service Now**, when prompted.
11. From the **Install Products** menu, select **HASP Network Monitor**. Follow the on-screen instructions provided.
12. Once the above is complete, exit the menu system completely and remove the installation CD.
13. Map a drive letter to the shared **Auto Time** folder that was created in Part 1, step 5.
14. Run the **Auto:Time** software for the first time.
15. When prompted, locate the **Auto:Time** system file, using the mapped drive created in Part 2, step 13.
16. Once complete, the software loads normally.

#### Notes:

Default installation paths;

App files:        \\Auto Time\Auto Time Software\  
Db files:         \\Auto Time\Auto Time Software\  
                  \

The dealer website address and email address will be populated automatically within the Help> About screen.



## Client / Server Upgrade from t5 - HASP on Server (Part 1)

The following instructions should be followed to upgrade a **timeware 5** Client/Server 'installation to a Client/Server 'Premium' installation (HASP on Server):

The following procedure assumes that the Server is storing **timeware 5** databases only and has no **timeware 5** applications installed.

### Part 1: Server Installation Procedure.

1. Insert the installation CD into the Server, select the **Install Products** menu and select **HASP Device Drivers**. Follow the on-screen instructions provided.
2. Insert the USB dongle into the Server and wait for 30 seconds for the device to be initialised.
3. From the **Install Products** menu, select **HASP License Manager**. Follow the on-screen instructions, setting the application to **Run as a Service** and selecting **Yes** to **Start Service Now**, when prompted.
4. From the **Install Products** menu, select **HASP Network Monitor**. Follow the on-screen instructions provided.
5. Once the above is complete, exit the menu system completely and remove the installation CD.

This completes Part 1 of the procedure.



## Client / Server Upgrade from t5 - HASP on Server (Part 2)

### Part 2: Client Installation Procedure.

6. Insert the installation CD into the Client PC, select the **Install Products** menu and select **Auto:Time Software**.
7. Follow the on-screen instructions and leave all options at their defaults unless stated otherwise. Ensure the **Application Only** option is selected at the appropriate time.
8. Toward the end of the installation procedure, the HASP device drivers will be installed. Follow the on-screen instructions provided.
9. Once the above is complete, exit the menu system completely and remove the installation CD.
10. Run the **Auto:Time** software for the first time.
11. When prompted, locate the original **timeware 5** system file using the mapped drive that should have been created during the original **timeware 5** installation.
12. When prompted, select **Yes** to upgrade software.
13. Once complete, the software loads normally.

### **Notes:**

Default installation paths;

Old t5 apps on Client PC:	\\Program Files\\NMD\\Timeware 5\\
Old t5 db files on Server:	\\Program Files\\NMD\\Timeware 5\\
New apps on Client PC:	\\Auto Time\\Auto Time Software\\
New db files on Server:	\\Program Files\\NMD\\Auto Time\\

The dealer website address and email address will be populated automatically within the Help> About screen.



## Client / Server Upgrade from t5 - HASP on Client

The following instructions should be followed to upgrade a **timeware 5** Client/Server installation to a Client/Server **Premium** installation (HASP on Client):

The following procedure assumes that the Server is storing **timeware 5** databases only and has no **timeware 5** applications installed.

1. Insert the installation CD into the Client PC, select the **Install Products** menu and select **Auto:Time Software**.
2. Follow the on-screen instructions and leave all options at their defaults unless stated otherwise. Ensure the **Application Only** option is selected at the appropriate time.
3. Select the **Hasp Device Drivers** option & install the HASP device drivers, following the on-screen instructions provided.
4. Insert the USB dongle into the Server and wait for 30 seconds for the device to be initialised.
5. From the **Install Products** menu, select **HASP License Manager**. Follow the on-screen instructions, setting the application to **Run as a Service** and selecting **Yes to Start Service Now**, when prompted.
6. From the **Install Products** menu, select **HASP Network Monitor**. Follow the on-screen instructions provided.
7. Once the above is complete, exit the menu system completely and remove the installation CD.
8. Run the **Auto:Time** software for the first time.
9. When prompted, locate the original **timeware 5** system file using the mapped drive that should have been created during the original **timeware 5** installation.
10. When prompted, select **Yes** to upgrade software.
11. Once complete, the software loads normally.

### Notes:

Default installation paths;

Old t5 apps on Client PC:	\Program Files\NMD\Timeware 5\
Old t5 db files on Server:	\Program Files\NMD\Timeware 5\
New apps on Client PC:	\Auto Time\Auto Time Software\
New db files on Server:	\Program Files\NMD\Auto Time\

The dealer website address and email address will be populated automatically within the Help> About screen.



## Upgrading from an earlier version (5.0.x)

The following instructions should be followed to perform an upgrade from an earlier version of **Auto:Time Premium** or **Auto:Time Express**, (versions 5.0.x).

The following procedure is based on a Single User installation, however the basis remains much the same for Client installations also.

1. Insert the installation CD, select the **Install Products** menu and select **Auto:Time Software**.
2. Follow the on-screen instructions and leave all options at their defaults unless stated otherwise.
3. Ensure the application path is changed to the existing application path. This will be either of the following defaults;  
C:\Program Files\Auto Time\Auto Time Express  
C:\Program Files\Auto Time\Auto Time Premium
4. Ensure the **Application Only** option is selected at the appropriate time.
5. Select the **Hasp Device Drivers** option & install the HASP device drivers, following the on-screen instructions provided.
6. Once the installation is complete, exit the menu system completely and remove the installation CD.
7. Insert the USB dongle into the computer and wait for 30 seconds for the device to be initialised.
8. Run the **Auto:Time** software as normal.

### Notes:

Default installation path;

\Program Files\Auto Time\Auto Time Express\  
\Program Files\Auto Time\Auto Time Premium\

The dealer website address and email address will be populated automatically within the Help> About screen.

After completing the upgrade, two sets of shortcuts will be present on the windows **Start\All Programs\Auto Time** menu. Although both sets of shortcuts will work it is recommended that the old set be removed to avoid any confusion for the end user.

The old set of shortcuts will be listed within **Start\All Programs\Auto Time\Auto Time Premium**, whereas the new set will be listed under **Start\All Programs\Auto Time\Auto Time Software**.